
tr064

Release 0.1.1

Oct 13, 2020

Contents

1	Installation	3
1.1	TR-064 API	3
1.2	Examples	5
	Python Module Index	9
	Index	11

This package provides a very lightweight and straight-forward [TR-064](#) client, that pulls every information about supported services from the routers description files.

Note: This documentation is a work in progress. Feedback and revisions are most welcome!

CHAPTER 1

Installation

Easiest way to install is to use `pip`:

```
$ python3 -m pip install tr064
```

To update a previous version:

```
$ python3 -m pip install --upgrade tr064
```

1.1 TR-064 API

1.1.1 General usage

Create a client connection to the router:

```
import tr064

client = tr064.Client('username', 'password', 'http://192.168.178.1:49000')

res = client.InternetGatewayDevice.DeviceInfo.GetInfo()
print(res.NewManufacturerName)
```

Actions (functions) are executed by append device, service and action to the client:

```
Client.DeviceName.ServiceName.ActionName(Arguments, ...)
```

If a service is offered multiple times, actions can be accessed by the zero-based square bracket operator:

```
Client.DeviceName.ServiceName[1].ActionName(Arguments, ...)
```

See more *Examples*.

Note: If services, actions or arguments contain a minus sign –, it must be replaced with an underscore _ and vice versa.

1.1.2 API

Client

class `tr064.client.Client` (*username, password, base_url='https://192.168.178.1:49443'*)
TR-064 client.

Parameters

- **username** (*str*) – Username with access to router.
- **password** (*str*) – Password to access router.
- **base_url** (*str*) – URL to router.

Exceptions

TR-064 exceptions.

exception `tr064.exceptions.TR064Exception`
TR-064 base exception.

exception `tr064.exceptions.TR064UnknownDeviceException`
TR-064 unknown device exception.

exception `tr064.exceptions.TR064UnknownServiceException`
TR-064 unknown service exception.

exception `tr064.exceptions.TR064UnknownServiceIndexException`
TR-064 unknown service index exception.

exception `tr064.exceptions.TR064UnknownActionException`
TR-064 unknown action exception.

exception `tr064.exceptions.TR064UnknownArgumentException`
TR-064 unknown argument exception.

exception `tr064.exceptions.TR064MissingArgumentException`
TR-064 missing argument exception.

Note: All following classes are never used directly! They are only documented for the sake of completeness.

Device

class `tr064.device.Device` (*xml, auth, base_url*)
TR-064 device.

Parameters

- **xml** (*lxml.etree.Element*) – XML device element

- **auth** (*HTTPBasicAuthHandler*) – HTTPBasicAuthHandler object, e.g. HTTPDigestAuth
- **base_url** (*str*) – URL to router.

Service

class tr064.service.**Service**(*auth, base_url, service_type, service_id, scpurl, control_url, event_sub_url*)
TR-064 service.

Action

class tr064.action.**Action**(*xml, auth, base_url, name, service_type, service_id, control_url*)
TR-064 action.

Parameters

- **xml** (*lxml.etree.Element*) – XML action element
- **auth** (*HTTPBasicAuthHandler*) – HTTPBasicAuthHandler object, e.g. HTTPDigestAuth
- **base_url** (*str*) – URL to router.
- **name** (*str*) – Action name
- **service_type** (*str*) – Service type
- **service_id** (*str*) – Service ID
- **control_url** (*str*) – Control URL

Helper

class tr064.attribute_dict.**AttributeDict**
Direct access dict entries like attributes.

class tr064.service_list.**ServiceList**
Service list.

1.2 Examples

All devices and services used in the following examples are taken from the [TR-064 Description XML](#). Used actions are described in the XML referred with the SCPDURL element of each service. More details about the action can be obtained from the router manufacturer.

Devices/Services/Actions:

- *InternetGatewayDevice*
 - *DeviceInfo*
 - * *GetInfo*
 - * *GetSecurityPort*
- *LANDevice*

- *Hosts*
 - * *GetHostNumberOfEntries/GetGenericHostEntry*
- *WLANConfiguration*
 - * *GetInfo/SetEnable*

1.2.1 InternetGatewayDevice

DeviceInfo

Support urn:DeviceInfo-com:serviceId:DeviceInfo1.

GetInfo

Getting router information:

```
res = client.InternetGatewayDevice.DeviceInfo.GetInfo()
print('ManufacturerName', res.NewManufacturerName)
print('ManufacturerOUI', res.NewManufacturerOUI)
print('ModelName', res.NewModelName)
print('Description', res.NewDescription)
```

GetSecurityPort

Get port for secure access:

```
unsafe_client = tr064.Client('username', 'password', 'http://192.168.178.1:49000')
res = unsafe_client.InternetGatewayDevice.DeviceInfo.GetSecurityPort()

safe_client = tr064.Client('username', 'password', 'https://192.168.178.1:{}'.
    ↪format(res.NewSecurityPort))
```

1.2.2 LANDevice

Hosts

GetHostNumberOfEntries/GetGenericHostEntry

List all assigned network devices:

```
number_of_entries = client.LANDevice.Hosts.GetHostNumberOfEntries()
for index in range(int(number_of_entries.NewHostNumberOfEntries)):
    host = client.LANDevice.Hosts.GetGenericHostEntry(NewIndex=index)
    print(host.NewIPAddress, host.NewMACAddress, host.NewHostName)
```

WLANConfiguration

GetInfo/SetEnable

Enable third WLAN device if not enabled:

```
info = client.LANDevice.WLANConfiguration[2].GetInfo()
if not bool(info.NewEnable):
    client.LANDevice.WLANConfiguration[2].SetEnable(NewEnable=1)
```


t

`tr064.exceptions`, 4

A

Action (*class in tr064.action*), 5

AttributeDict (*class in tr064.attribute_dict*), 5

C

Client (*class in tr064.client*), 4

D

Device (*class in tr064.device*), 4

S

Service (*class in tr064.service*), 5

ServiceList (*class in tr064.service_list*), 5

T

tr064.exceptions (*module*), 4

TR064Exception, 4

TR064MissingArgumentException, 4

TR064UnknownActionException, 4

TR064UnknownArgumentException, 4

TR064UnknownDeviceException, 4

TR064UnknownServiceException, 4

TR064UnknownServiceIndexException, 4